

## SpinFire Floating License Setup Procedures

### FlexLM Server

#### STEP 1 - Download the FlexLM Server Code

[http://iq.actify.com/iq/FloatingLicenseSupport/SFFloatingInst\\_840.exe](http://iq.actify.com/iq/FloatingLicenseSupport/SFFloatingInst_840.exe)

#### STEP 2 - FlexLM Installation Instructions

- Stop current Actify Floating License Server process if running
  - Via Control Panel->Administrative Tools->Services
  - Start the Task Manager and make sure all *lmgrd.exe* and *actifyd.exe* processes are terminated.
- Install on the desired server machine into the following location (Default);
  - C:\Program Files\Actify\Floating License Manager
- Go to C:\Program Files\Actify\Floating License Manager
- Copy the "sfpflv2.dat" file to this folder
- Run "lmtools.exe"
- Select the "Config. Services" Tab
- Make sure the Path to the "*lmgrd.exe*" and "*sfpflv2.dat*" files are correct
- Check "*Use Services*" and "*Start Server at Power Up*" at the bottom
- Select the "Save Service" button
- Select "Start/Stop/Reread" tab and select "Start Server"
- Select the "ReRead License File" button
- Select the "Server Status" tab and "*Perform Status Enquiry*"
- You should get back a listing of all your available licenses, similar to below;

```
-----
Status
-----
Flexible License Manager status on Wed 4/25/2007 08:56
[Detecting lmgrd processes...]
License server status: 27000@Server
  License file(s) on vassello-xp: C:\Program Files\Actify\Floating License
Manager\sfpflv2.dat:

Server: license server UP (MASTER) v9.2

Vendor daemon status (onServer):

  actifyd: UP v9.2

Feature usage info:

Users of CATIA: (Total of 1 license issued; Total of 0 licenses in use)
Users of CATIA_V2: (Total of 1 license issued; Total of 0 licenses in use)
Users of 3DView35-Core: (Total of 1 license issued; Total of 0 licenses in use)
```

### SpinFire Client – Windows XP

#### STEP 3 - Client Activation

##### Automatic Activation

- Obtain the License file, license.al, from Actify
- Copy this file to the "C:\Documents and Settings\All Users\Application Data\Actify\SpinFire Professional" folder of each SpinFire client
- Start the SpinFire Application
- SpinFire will now obtain a license from the server, and automatically Activate when opened for the first time

NOTE: The "sfpflv2.dat" file will automatically be extracted from the license.al file and copied to the same folder, "C:\Documents and Settings\All Users\Application Data\Actify\SpinFire Professional"

## SpinFire Client - VISTA

### STEP 3 - Client Activation

#### Automatic Activation

- Obtain the License file, license.al, from Actify
- Copy this file to the "C:\ProgramData\Actify\SpinFire Professional" folder of each SpinFire client
- Start the SpinFire Application
- SpinFire will now obtain a license from the server, and automatically Activate when opened for the first time

NOTE: The "sfpflv2.dat" file will automatically be extracted from the license.al file and copied to the same folder, "C:\ProgramData\Actify\SpinFire Professional"